

Photoshop Shortcuts for X-keys

Document Shortcuts

*Photoshop	Drag and Drop or Use the File and Directory tabs to find it
*Photoshop 32 bit	Drag and Drop or Use the File and Directory tabs to find it
My Pictures Folder	Drag and Drop or Use the File and Directory tabs to find it
New Document	Ctrl + N
Open	Ctrl + O
Close	Ctrl + W
Close All	Alt + Ctrl + W
Quit	Ctrl + Q
Save	Ctrl + S
Save As	Shift + Ctrl + S
Save for Web	Alt + Shift + Ctrl + S
Copy	Ctrl + C
Paste	Ctrl + V
New File & Paste – for screenshots	Ctrl + N Enter Ctrl + V

*When programming a specific program to open with X-keys, use the Shortcuts tab.

Panel Shortcuts

New Layer	Shift + Ctrl + N
Duplicate Layer	Shift + Ctrl + '
Clipping Mask	Alt + Ctrl + G
Brushes Panel	F5
*Copy Layer Style	Shift + Ctrl + 1
*Paste Layer Style	Ctrl + `
Flatten Image	Alt + Ctrl + P

*The Copy/Paste Layer Style, Duplicate Layer and Flatten Image do not have default shortcuts in Photoshop, so you have to assign your own and then program it to your X-keys (what's shown above is what I set my shortcut as) – you can find where to edit these under “edit – Keyboard Shortcuts”

Adjustment Shortcuts

Auto Tone	Shift + Ctrl + L
Hue/Saturation Adjustment	Ctrl + U
Levels	Ctrl + L

Viewing Shortcuts

Zoom In	Ctrl + or Alt + Scroll Forward with Mouse
Zoom Out	Ctrl – or Alt + Scroll Backwards with Mouse
Fit on Screen	Ctrl + 0
Scroll Right/Left	Ctrl + Scroll with Mouse

Photoshop Shortcuts for X-keys

Image Shortcuts

Image Size	Alt + Ctrl + I
*Image Size 1200	Alt + Ctrl + I 1200 Enter
**Image Size 200	Alt + Ctrl + I Enter Tab Tab 200 Enter
**Image Size 45	Alt + Ctrl + I Enter Tab Tab 45 Enter
Canvas Size	Alt + Ctrl + C
Inverse	Shift + Ctrl + I
Refine Edge	Alt + Ctrl + R
Deselect	Ctrl + D
Select All	Ctrl + A

*Image Size 1200, 200, and 45 require you to switch between **Keystrokes** to **Text** when programming your X-keys

**Image Size 200 and 45 require you to hit the tab key twice before entering in the desired number, this will change the height dimension first

Tools Shortcuts

*Brush Tool	Shift + B
*Eraser Tool	Shift + E
*Pen Tool	Shift + P
*Shape Tool	Shift + U
*Gradient Tool	Shift + G
Move Tool	V
*Magic Wand	Shift + W
*Crop Tool	Shift + C
*Eyedropper Tool	Shift + I
*Text Tool	Shift + T
Quick Mask	Q

*Using the Shift key allows you to switch between all tools within that particular group

Edit Shortcuts

Undo	Ctrl + Z
Transform	Ctrl + T
Inverse	Shift + Ctrl + I
Refine Edge	Alt + Ctrl + R
Deselect	Ctrl + D
Select All	Ctrl + A
*Alt	Alt
*Shift	Shift
*Control	Control
Fill with Background or Foreground Color	Shift + F5
**Trim	Alt + Ctrl + Y
**Rotate	Shift + Ctrl + R
**Scale	Shift + Ctrl + =

Photoshop Shortcuts for X-keys

**Skew	Shift + Ctrl + -
**Unsharp Mask	Shift + Ctrl + M

*Helpful hint – On the Alt, Shift and Control keys, if you separate the up and down keystrokes it will hold that key down until you release it. This assists with zooming or selecting more than one layer/object.

**The Trim, Rotate, Scale, Skew and Unsharp Mask do not have default shortcuts in Photoshop, so you have to assign your own and then program it to your X-keys (what's shown above is what I set my shortcut as) – you can find where to edit these under “edit – Keyboard Shortcuts”